

# **DDBSP 2015**

# **Explorer Version**

# **Installation Notes**

**DDBSP** - Dortmund Data Bank Software Package



DDBST Software & Separation Technology GmbH

Marie-Curie-Straße 10

D-26129 Oldenburg

Tel.: +49 441 36 18 19 0


Fax: +49 441 36 18 19 10

[support@ddbst.de](mailto:support@ddbst.de)


[www.ddbst.de](http://www.ddbst.de)

## Software Installation


1. Unpack the zip archive to a local folder. The following files are shown:




2. Run *SetupStarter.exe* to initialize the setup procedure.



3. The button *DDBSP 2015 Explorer Version* brings up a context menu with some options:




4. Click the *Start DDB/DDBST Installation* menu entry. The setup needs administrator privileges and therefore the Windows user access control (UAC) may request additional rights.
5. The setup starts with the *Welcome* dialog:




Click on *Next* to continue.


6. To proceed with the program setup please read the license agreement carefully, accept it and click *Next*.




7. The recommended installation folder for the DDB/DDBSP Explorer Version is a subfolder of the Windows standard program folder. It can be changed by using the *Browse* button.




8. If an older installation is overwritten, the creation of backups for files being replaced during the installation can be selected as an installation option.




- The next step allows selecting a name for the Windows program manager group. Click *Next* to continue.




- Please evaluate the setup options carefully and select *Back* if settings have to be changed.




11. Almost finally: Clicking on the *Install* button starts the installation.




12. After all files are copied, the components are registered within Windows. This step is marked by the *Update System Configuration* message.




13. The final dialog is the *Finished* dialog. It allows displaying the program manager dialog or starting the DDBSP JumpStart program directly. Please note that in case of an active UAC the programs will be started with administrator privileges.



14. The program manager group contains the following entries:



15. The first run of the DDBSP *JumpStart* brings up a settings dialog:




## Requesting and Installing a License


1. Start the license manager from the *Additional* folder in the Windows program manager group.



2. Switch to the *Registration* page and fill the Company name or “Home” and a valid email address. Click then on *Online Registration Request* to send the license request.




3. The program shows the data sent to DDBST GmbH:






4. The DDBST license management system now creates the license in an automatic process. Typically within less than five minutes you should receive an email which looks like this



and contains an appendix with the zipped license file. Save this appended archive and unzip the license file.

5. Return to the *RLM Client Configuration* program and click on the *Add License* button on the *Licenses* page and select the license file:



This was the final step in the installation. The *Display Product* button can now be used to display the available licenses.

## Final Comments

The explorer edition is a limited version of the Dortmund Data Bank and the DDB software package and is intended only for test purposes and to show the possibilities of the full versions.

In case of any questions, comments or requests please don't hesitate to get in touch with us using [support@ddbst.com](mailto:support@ddbst.com) or the contact form on our web site [www.ddbst.de](http://www.ddbst.de).