

DDB/DDBSP 2021 Installation Guide

DDBSP - Dortmund Data Bank Software Package



DDBST

Dortmund Data Bank
Software & Separation
Technology

DDBST - Dortmund Data Bank Software & Separation Technology GmbH

Marie-Curie-Straße 10

D-26129 Oldenburg

Tel.: +49 441 36 18 19 0

Fax: +49 441 36 18 19 10

support@dbst.com

www.dbst.com

1	Installation Requirements	3
2	Installation of DDB/DDBSP	3
2.1	Welcome	3
2.2	End-User License Agreement.....	4
2.3	GDPR Privacy Notice for EU Residents	5
2.4	Setup Type	6
2.5	Installation Folder.....	6
2.6	DDB Configuration	7
2.7	License Server	8
2.8	Configure Shortcuts.....	9
2.9	File Associations.....	9
2.10	Ready to Install	10
2.11	Installation Completed	11
3	DDB/DDBSP 2021 – Silent Installation	11
3.1	Silent Install.....	11
Example	12

1 Installation Requirements

To install DDB/DDBSP administrative rights are required. On *Terminal Server* editions the setup has to be started from the “add/remove programs” dialog of the control panel.

DDB/DDBSP needs a valid license to run. The license can reside on the local computer (single-user license) or can be served by a license server (concurrent license). The installation of a license is described in the *RLM License Configuration* documentation.

An officially supported Microsoft Windows version at release time is required.

2 Installation of DDB/DDBSP

The DDB/DDBSP setup can be started within the *DDBSP Setup* program (see Figure 1).




Figure 1

In **single-user** setups the option *Start License Server Installation* is not available.

The installation guides can be displayed using the *DDBSP Installation Guides* sub-menu.

2.1 Welcome

The setup starts with the *Welcome* screen shown in Figure 2. Click on the *Next* button to proceed.




Figure 2

2.2 End-User License Agreement

The next step in the setup process is the display of the end-user license agreement (see Figure 3).




Figure 3

Read the agreement carefully and accept the license agreement by clicking the radio button as shown in Figure 4. The radio buttons will be enabled if the end of the text is visible.

I accept the terms in the License Agreement

Figure 4

Click the now enabled *Next* button to proceed with the next step of the installation.

It is also possible to copy the text to the Windows clipboard by

1. clicking in the text area,
2. pressing *Control-A* to select the entire text and
3. pressing *Control-C* to copy the marked text to clipboard.

2.3 GDPR Privacy Notice for EU Residents

Now the setup asks if you are a resident of a European country (see Figure 5).




Figure 5

If you confirm that you are a resident of a European country, the setup displays the dialog shown in Figure 6.



Figure 6

Read the agreement carefully before continuing with the setup.

2.4 Setup Type

In the next dialog you can choose the setup type (see Figure 7). If you choose *Typical* then only the license server can be configured before the installation process starts. If you choose *Custom* then all dialogs described in the following sections will be displayed.




Figure 7

2.5 Installation Folder




Figure 8

The next dialog (Figure 8) asks for the destination folder of the application files.

2.6 DDB Configuration

The setup now displays the *DDB Configuration* dialog (Figure 9).




Figure 9

The dialog is used to specify the path to the folder where the public DDB files will be installed and the paths to the private DDB and the DDB specific clipboard folder. Non-existing directories will be created. The folders can be changed by changing the contents of the edit fields or by selecting the *Browse* buttons.

For the clipboard folder the default setting is to use the Windows TEMP folder (which may be user specific). To select a different folder switch from *Default* to *Custom* and change the folder settings (see Figure 10).




Figure 10

The clipboard folder must be writable for all DDBSP users.

The default location for the public DDB folder is a sub-folder of the programs folder. The default location for the private DDB folder is a DDBSP 2021 specific sub-folder of the global application data folder.

In some editions of DDBSP the *DDB Configuration* dialog is missing.

All three folders must be different, otherwise the software will show unexpected behavior.

If the *Artist Structure* package is part of the setup, then the optional *NCI structure database* can be installed.

2.7 License Server

The *Select License Server* dialog (see Figure 11) will come up next.




Figure 11

For users of a **single-user** license all entries should be left empty. For users of a **concurrent** license the location of the license server has to be specified either by specifying the name or the IP address (IPv4) of the machine where the license server has been installed. The IP address is essentially a four-byte number where the single bytes are values from 0 to 255. Please ask your network supervisor for the name or IP address of the license server machine. If the license server is installed on the same machine either “127.0.0.1” as server IP address or “localhost” as server name has to be used.

If you want to use the default port (5053) for the communication between application and license server then leave the field *License Server Port* empty.

Please note that the setup does not check if the server name or IP address is valid and points to an existing machine. In addition, it is not checked if client and server use the same port. If any of the specification is incorrect, the DDB software won't work. The license server specification can be modified after the installation by the *RLM Client Configuration* program. Use the page *Licenses* to review and change the license server location or manage local licenses. The program is located in *Additional* folder of the DDBSP start menu folder.

In some editions of DDBSP the *Select License Server* dialog is missing.

2.8 Configure Shortcuts

The *Configure Shortcuts* dialog (see Figure 12) allows the user to place a shortcut to the DDBSP start menu folder on the desktop.




Figure 12

2.9 File Associations

In the *Select File Associations* dialog (see Figure 13) the user can select which file types should be associated with DDBSP. Depending on the packages included in the setup not all file types may be active.




Figure 13

2.10 Ready to Install

In the *Ready to Install* dialog (see Figure 14) click on the *Install* button to start the installation.




Figure 14

Depending on the system settings the *User Account Control* (UAC) will ask for permission to proceed with the installation (running elevated).

Now the files will be installed and the system will be configured (see Figure 15). This can take several minutes.




Figure 15

2.11 Installation Completed

The last dialog of the setup allows the user to set some options (see Figure 16).




Figure 16

The option *View release notes (PDF)* has to be activated to see the release notes for the current version.

The option *Launch DDBSP JumpStart* runs the DDBSPJumpStart program immediately.

3 DDB/DDBSP 2021 – Silent Installation

This section refers mainly to system administrators who want to automate the install procedure of DDB/DDBSP.

The DDBSP setup is based on MSI. The EXE Bootstrapper supports all *msiexec* command-line options.

3.1 Silent Install

For an automated installation some properties can be specified in the command line.

The following properties are supported:

- **LICENSE_AGREED**
For passive installations set the value to “1”. Otherwise, the installation will fail.
- **DDBPTH**
This is the installation folder for the public DDB files. The default value is the sub-folder “DDB\” of APPDIR.
- **DDBPRV**
This is the folder for private DDB files. A user must have write access to this folder in order to enter private experimental or component data. The default value is the sub-folder “DDBST GmbH\DDBSP2021\DDBPRV\” of the global application data folder.
- **DDBSCR**
This is the folder for temporary files. A user must have write access to this folder. If the value is empty %TEMP% is used. The default value is empty.

- **DOINSTALLNCI**
If *Artist Structure* is part of the setup an optional structure database can be installed. The installation is optional because the file size is about 225 MB. Set the value to “0” to have the database *not* installed. The default is to install the database.
- **APPDIR**
This is the complete path to the target folder for the program files. The default value is “%ProgramFiles(x86)%\DDBST GmbH\DDPSP2021”.
- **CREATE_DESKTOP_SH**
Set the value to “0” to *not* create a shortcut to the start menu folder on the desktop. The default is to create a shortcut on the desktop.
- **ASP_CONFIDENT**
The contents of this variable is written as comment on top of each Aspen-INP file created by DDBSP. To get multi-line text the occurrence of “\r” will be handled as line break. The default value is empty.
- **ASP_PURE**
This variable contains the Aspen PURE databases which are used in Aspen-INP export. The entries have to be separated by semicolon. The default value is “PURE;INORGANIC;AQUEOUS”.
- **DEMO_PRV_TEXT**
The contents of this variable will be displayed in the data set text output of private data sets that do not contain any data point. The default value is empty.
- **RLM_SERVER**
This variable holds the license server location. It can either be specified by the IP address (IPv4) or by the name of the server computer. The default value is empty.
- **RLM_PORT**
This variable can be used to specify the port for the communication between client and license server. The default value is empty.
- **VIEWREADME**
Set this variable to “” to *unselect* the option to display the release notes in the *Completed* dialog.
- **RUNAPPLICATION**
Set this variable to “” to *unselect* the option to run the DDBSPJumpStart program in the *Completed* dialog.

Example

DDB/DDBSP is installed with

- public and private database folder and temporary folder as sub-folder of “C:\DDBSP”
- default installation folder for the program files, create shortcuts to the start menu folder on the desktop
- not installing the NCI structure database
- use “myserver” as license server on port 34521
- a multi-line Aspen-INP header and the Aspen PURE databases PURE34, INORGANIC and AQUEOUS

The silent installation is started using the following program call:

```
MainSetup2021.exe /passive LICENSE_AGREED="1" DDBPTH="C:\DDBSP\DDB\  
DDBPRV="C:\DDBSP\PRIVATE\  
DDBSCR="C:\DDBSP\SCRATCH\  
DOINSTALLNCI="0"  
RLM_SERVER="myserver" RLM_PORT="34521"  
ASP_CONFIDENT="Note: This file contains\rConfidential Information."  
ASP_PURE="PURE34;INORGANIC;AQUEOUS"
```